

Screen Pixel Ruler [master]

Stewart Cossey

2021-12-04

Contents

Overview	5
Features	5
Installation	5
User Interface	7
Guidelines	9
Adding and Removing Guidelines	9
Clearing Guidelines	9
Importing and Exporting Guidelines	9
Global Shortcuts	11
Configuration	13
Options	13
Location	14
Themes	15
Location	15

Overview

Screen Pixel Ruler is a on screen ruler that can assist in measuring elements from web pages, documents or software which does not implement a native ruler. Based on .NET Core 3.1 and inspired by MioPlanet PixelRuler, this software is supported on Windows 7 and higher.

Features

- Global hotkeys to trigger functionality when other software is in focus.
- Rotatable vertical or horizontal ruler. **Ctrl + Shift + Alt + R**
- Customizable ruler themes.
- Freezable position. **Ctrl + Shift + Alt + F**
- Guideline system that can lock the mouse cursor horizontally or vertically
- Position 0 of the ruler to the current cursor location. **Ctrl + Shift + Alt + S**

A list of all shortcuts can be found [here](#).

Installation

Screen Pixel Ruler can be installed from either the Installer or via Chocolatey Package Management by running the command `choco install screenpixelruler`. Both the installer and package will install the .NET Core 3.1 runtime if it is not present.

User Interface

The user interface consists of a single ruler that can be displayed either horizontally or vertically.



Figure 1: The Ruler user interface.

Pressing the secondary mouse button on the ruler will display a context menu called the *Ruler Menu*. The secondary button is usually the right mouse button.

The ruler can be rotated using the `Ctrl + Shift + Alt + R` key combination or by the *Rotate* menu item in the *Ruler Menu*.

It is not possible to have both a vertical and a horizontal ruler displayed at the same time.

Guidelines

Guidelines allow you to mark specific points on the ruler.

Adding and Removing Guidelines

You can add and remove guidelines by using the Ruler Menu > Guidelines submenu. Adding a guideline will add a new guideline at the cursor position on the ruler.

Clearing Guidelines

Importing and Exporting Guidelines

Global Shortcuts

These shortcuts can be used even when the Screen Pixel Ruler is not focused.

Keystroke	Function
Ctrl + Shift + Alt + R	Change ruler rotation.
Ctrl + Shift + Alt + E	Flip ruler notch direction.
Ctrl + Shift + Alt + F	Freeze the position marker on the ruler.
Ctrl + Shift + Alt + S	Move position 0 of the ruler to the current mouse position.
Ctrl + Shift + Alt + X	Exit Screen Pixel Ruler 2.
Ctrl + Shift + Alt + A	Add Guideline at current position on the ruler.
Ctrl + Shift + Alt + D	Delete nearest Guideline from current position on the ruler.
Ctrl + Shift + Alt + G	Lock mouse position to nearest Guideline.

Configuration

You can access the configuration by right clicking the ruler and selecting *Options*. This will then display the *Options window* where you can change the configuration.




Figure 2: The options window.

Options

Theme

Allows you to change the theme of the ruler.

Primary Click, Middle Click, Button 4 Click, Button 5 Click

Allows you to assign mouse button clicking the ruler to specific functionality. Pressing and holding the primary click will allow you to move the ruler.

The primary click is determined by the *Select your primary button* option in the *Mouse Settings* on Microsoft Windows.

Location

Configuration is stored in two locations depending on if you installed from the installer or from the chocolatey package.

Installer: %appdata%\screenpixelruler\app.cfg

Chocolatey: %chocolateyinstall%\lib\screenpixelruler\tools\app.cfg

Themes

Themes can change the ruler colour, size or even the size of the ruler notches.

You can create your own themes for Screen Pixel Ruler. Themes have a **thm** file extension and are written in yaml.

Location

Themes are stored in the two locations, depending on if you installed from the installer or from the chocolatey package.

Installer: %appdata%\screenpixelruler

Chocolatey: %chocolateyinstall%\lib\screenpixelruler\tools